

---

# Kassow Robots

# PROFINET

Version: 1.0.0 EN1

Table of Contents

1 Introduction .....2

2 Kassow Profinet .....3

    2.1 Structure .....3

        2.1.1 IO Modules .....3

        2.1.2 User defined types .....3

    2.2 Profinet activation .....4

    2.3 Profinet variables .....4

        2.3.1 Map Profinet variable .....5

    2.4 Profinet usage in TIA portal .....5

    A Appendix KR Profinet network frame .....8

# 1 Introduction

Profinet (usually styled as PROFINET, as a portmanteau for Process Field Net) is an industry technical standard for data communication over Industrial Ethernet, designed for collecting data from, and controlling equipment in industrial systems, with a particular strength in delivering data under tight time constraints. The standard is maintained and supported by Profibus & Profinet International [de], an umbrella organization headquartered in Karlsruhe, Germany.

KassowRobots RCs provide the access to this realtime field bus by the use of specialised hardware extension (Hilscher cifX), available only for the dedicated controllers (it is not a part of the standard product KR RC).

The Profinet extension handles all necessary realtime requirements for the fieldbus and allows to integrate KassowRobots controllers with the existing Profinet infrastructures.

## 2 Kassow Profinet

### 2.1 Structure

#### 2.1.1 IO Modules

The robot Profinet data are organized into **12** modules. **7** modules serve for sharing the data from the robot to a PLC while **5** modules can be used to send data from a PLC to the robot. All modules are optional, but are fixed to a specific slot.

Slot	Name	Direction	Description
1	System State	Robot → PLC	Monitors robot and safety state
2	Joints Monitor	Robot → PLC	Monitors joint positions and dynamics
3	TCP Monitor	Robot → PLC	Monitors TCP kinematics and dynamics
4	IO Monitor	Robot → PLC	Monitors IO Board and Tool IO state
5	64x Bit Input	Robot → PLC	Input bit register allocated for user data
6	24x Int Input	Robot → PLC	Input integer register allocated for user data
7	24x Real Input	Robot → PLC	Input real register allocated for user data
8	System Control	PLC → Robot	Controls master speed
9	IO Control	PLC → Robot	Controls IO Board and Tool IO outputs
10	64x Bit Output	PLC → Robot	Output bit register allocated for user data
11	24x Int Output	PLC → Robot	Output integer register allocated for user data
12	24x Real Output	PLC → Robot	Output real register allocated for user data

Detailed information about each of the modules can be found in Appendix A.


#### 2.1.2 User defined types

In order to provide easier integration with PLCs, the structure of IO modules has been also expressed via user defined types (UDT). Once the user imports KR datastruct into PLC's programming environment, each module can be mapped into appropriate data type.

**Note:** For the *Profinet\_-KR\_-Datastruct.udt* file, please check with our online documentation or get in touch with our support line.

## 2.2 Profinet activation

Profinet needs to be enabled through the teach pendant UI prior its usage.



1. Select Profinet interface in Workcell.
2. Click enable to activated the Profinet.
3. Wait until the status is changed to Connected.



If Profinet interface is not available, your robot is probably not equipped with optional Profinet HW.

## 2.3 Profinet variables

The robot allows mapping of 6 Profinet modules (bit, int and real user data) into system variables. Each of these modules is represented as an array variable with one column of number data type.

System Variable	Data Type	Module	Direction	Length
Profinet Bit Output	Array	PLC → Robot	PLC → Robot	24
Profinet Int Output	Array	PLC → Robot	PLC → Robot	64
Profinet Float Output	Array	PLC → Robot	PLC → Robot	64
Profinet Bit Input	Array	Robot → PLC	Robot → PLC	24
Profinet Int Input	Array	Robot → PLC	Robot → PLC	64
Profinet Float Input	Array	Robot → PLC	Robot → PLC	64


### 2.3.1 Map Profinet variable

1. Select Profinet interface int Workcell.
2. Click Map Profinet Variable.
3. Select desired mapping, enter variable name and click Create.


## 2.4 Profinet usage in TIA portal

1. Install Kassow Robots GSD file to TIA Portal.


**Note:** For the *gsdml-v2.35-kassow\_robots-axxx-20210602.xml* file, please check with our online documentation or get in touch with our support line.




2. Add KRv1.0 device to network.




3. Connect KR device to PLC.



4. Add desired IO modules to KR device.



5. Compile HW configuration.
6. Download HW configuration to PLC.
7. Go online and check status.





## A Appendix - KR Profinet network frame

System State																																
Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	Major version (uint8_t)								Minor version (uint8_t)								Reserved															
32	Robot milliseconds (uint16_t)																Robot seconds (uint8_t)								Robot minutes (uint8_t)							
64	Robot hours (uint8_t)								Reserved																Robot days (uint16_t)							
96	Robot current [A] (float)																															
128	Robot mode (uint8_t)								Robot state (uint8_t)								Program state (uint8_t)								Reserved							
160	EB	PB		TB	BB	Reserved			Reserved																							
192	Master Speed (float)																															
224	Safety mode (uint8_t)								Reserved																ES	PS	SS	Reserved				

Joints Monitor																																
Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	Joint 1 position [rad] (float)																															
32	Joint 2 position [rad] (float)																															
64	Joint 3 position [rad] (float)																															
96	Joint 4 position [rad] (float)																															
128	Joint 5 position [rad] (float)																															
160	Joint 6 position [rad] (float)																															
192	Joint 7 position [rad] (float)																															
224	Joint 1 velocity [rad/s] (float)																															
256	Joint 2 velocity [rad/s] (float)																															
288	Joint 3 velocity [rad/s] (float)																															
320	Joint 4 velocity [rad/s] (float)																															
352	Joint 5 velocity [rad/s] (float)																															
384	Joint 6 velocity [rad/s] (float)																															
416	Joint 7 velocity [rad/s] (float)																															
448	Joint 1 current [A] (float)																															
480	Joint 2 current [A] (float)																															
512	Joint 3 current [A] (float)																															
544	Joint 4 current [A] (float)																															
576	Joint 5 current [A] (float)																															
608	Joint 6 current [A] (float)																															
640	Joint 7 current [A] (float)																															
672	Joint 1 temperature [°C] (float)																															
704	Joint 2 temperature [°C] (float)																															
736	Joint 3 temperature [°C] (float)																															
768	Joint 4 temperature [°C] (float)																															
800	Joint 5 temperature [°C] (float)																															
832	Joint 6 temperature [°C] (float)																															
864	Joint 7 temperature [°C] (float)																															

TCP Monitor																																
Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	TCP position X [m] (float)																															
32	TCP position Y [m] (float)																															
64	TCP position Z [m] (float)																															
96	TCP position OR [rad] (float)																															
128	TCP position OP [rad] (float)																															
160	TCP position OY [rad] (float)																															
192	TCP velocity X [m/s] (float)																															
224	TCP velocity Y [m/s] (float)																															
256	TCP velocity Z [m/s] (float)																															
288	TCP velocity OR [rad/s] (float)																															
320	TCP velocity OP [rad/s] (float)																															
352	TCP velocity OY [rad/s] (float)																															
384	TCP force X [N] (float)																															
416	TCP force Y [N] (float)																															
448	TCP force Z [N] (float)																															
480	TCP torque X [N.m] (float)																															
512	TCP torque Y [N.m] (float)																															
544	TCP torque Z [N.m] (float)																															
576	TCP force scalar [N] (float)																															

IO Monitor																																
Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	IOB digital inputs (bits)															IOB safe inputs (bits)								Reserved								
32																IOB current input 1 [A] (float)																
64																IOB current input 2 [A] (float)																
96																IOB voltage input 1 [V] (float)																



[illegible]

## System Control

Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	SSM																Reserved															
32	Master Speed																															

## IO Control

[illegible]

### 64 Bit Output

Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	0 to 31 bit output register (bits)																															
32	32 to 63 bit output register (bits)																															

24 Int Output

[illegible]

## 24 Real Output

Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31
0	Real 0 (int32_t)																															

Bit	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	
32																																	Real 1 (int32_t)
64																																	Real 2 (int32_t)
96																																	Real 3 (int32_t)
128																																	Real 4 (int32_t)
160																																	Real 5 (int32_t)
192																																	Real 6 (int32_t)
224																																	Real 7 (int32_t)
256																																	Real 8 (int32_t)
288																																	Real 9 (int32_t)
320																																	Real 10 (int32_t)
352																																	Real 11 (int32_t)
384																																	Real 12 (int32_t)
416																																	Real 13 (int32_t)
448																																	Real 14 (int32_t)
480																																	Real 15 (int32_t)
512																																	Real 16 (int32_t)
544																																	Real 17 (int32_t)
576																																	Real 18 (int32_t)
608																																	Real 19 (int32_t)
640																																	Real 20 (int32_t)
672																																	Real 21 (int32_t)
704																																	Real 22 (int32_t)
736																																	Real 23 (int32_t)